


NCVIP VIDEOCONFERENCE SCHEDULING

Module 1.1

Scheduling a NC Video over IP (NCVIP) Conference

Objectives: Understand the basic procedure required to successfully schedule a point-to-point or multi-point conference through the VNS (Video Network Services) Web Scheduler.

- Step 1. Connect to the VNS Web Scheduler.
- **Step 2.** Once you connect to the server you will see the following login screen. Enter your VNS supplied username and password. Click the Login button.




If you have successfully entered your username and password, you will see the following screen.





Step 3. To schedule a videoconference click "Create Conf". The following scheduling template appears. The template has two pages.



- **Step 4.** Enter the Reservation name in Step 2 of the template.
- Step 5. Select resources/codecs in Step 3 by clicking on each site's name. The sites are listed alphabetically. Sites with NCVIP as part of their name are VNS IP Video sites. To filter, type a string of letters such as ITS in the filter field and click the lightening bolt. Only sites with ITS in their name will appear in the list. To restore the full listing of sites click on the red X.






Step 6. Select Start time and End time in Step 4 by using the drop down lists. To stagger a site into or out of a conference, highlight the name of the site and set either the adjusted start time or end time.




Step 7. Choose a single date or a group of dates for a recurring conference in Step 5. To select all Thursdays and Fridays, click on the Day of the week in each month. Advance to the next month by clicking on arrows or using drop down selection.

Eliminate non-meeting days by clicking on the date to turn it white again or highlighting date in list and clicking on red X.





Step 8. An alternative way to schedule recurring conferences is to use the Range Tab at the bottom of the calendar.




Step 9. Click on Next at the bottom of the page to go to the second page of the scheduling template.





- **Step 10.** Select Setup time by using the drop down menu. All conferences have a minimum setup time of one minute per participating site and an automatic two-minute tear down time at the end of the conference. Setup and tear down time are considered part of the conference duration and can cause a denial. Sometimes denials can be resolved by adjusting the setup time.
- **Step 11.** Choose mode from drop down menu. Most conferences with NCVIP sites should be scheduled as voice activated but you can use Broadcast Lecturer.
- **Step 12.** Lecture cycle usually remains at auto but can be adjusted for Broadcast Lecturer mode conferences. Lecture cycle does not affect Voice Activated conferences.
- **Step 13.** To facilitate connection of multiple sites with different video algorithm capabilities, use Auto under Video Alg.
- Step 14. To select a continuous presence or CP (split screen) Layout click on the icon



- **Step 16.** All sites currently operate at 320 kb. Do not need to check "Use same speed for all participants".
- **Step 17.** Under name, if available, choose whether a site will connect by Customer Dial or BellSouth Dial (Auto connect) to connect to a conference. Some NCVIP sites only connect by Customer Dial.





- **Step 18.** The first Note section is sent with the email notification. The second Note section goes to the BellSouth technicians. You do not need to fill out both.
- **Step 19.** Click on Schedule button to begin the resolution process. Back returns you to the first page of the template. Cancel ends the scheduling process. DO NOT SAVE TEMPLATE BEFORE CLICKING ON SCHEDULE.

